SFM SDK Revision Notes

Version 1.2



Revision Notes

Software Version 1.2

2006-4-28

- Socket APIs are added. These APIs can be used when a module is connected to host PC through an Ethernet-to-Serial converter.
- UF_SearchModuleBySocket and UF_SearchModuleIDEx are added.
- UF_SetSecurityLevel and UF_GetSecurityLevel are added. Different security levels can be assigned to each user for 1:1 matching.
- The first reserved byte of UFUserInfo structure is used for storing the security level of the user.
- To support real-time monitoring, UF_ClearLogCache and UF_ReadLogCache are added
- UF_SetCustomLogField and UF_GetCustomLogField are added for custom log records.
- Access control APIs are added for BioEntry readers. Users can configure time schedules, holiday schedules, and access groups using these APIs.
- UF_ERR_ACCESS_NOT_GRANTED will be returned when access is not granted by time schedules and access groups.

Software Version 1.1

2005-12-2

- UF_Reset is added.
- UF_EnrollMultipleTemplates is added.
- UF_ReadOneTemplate is added.
- UF_DeleteOneTemplate and UF_DeleteMultipleTemplates are added.
- UF_EnrollTemplate and UF_ReadTemplate are changed to try extended data transfer protocol first.

© 2006 by Suprema Inc.

1

- numOfChar parameter is added to UF_SetWiegandIO and UF_GetWiegandIO. This parameter is used for ABA Track II output format.
- UF_INPUT_RESET is added to UF_INPUT_FUNC type.
- UF_OUTPUT_SYS_STARTED is added to UF_OUTPUT_EVENT type. This event occurs when the module is started.
- UF_SYS_WATCHDOG parameter is added.
- UF_WIEGAND_OUTPUT_ABA_TRACK_II is added to UF_WIEGAND_OUTPUT_MODE.
- The following bugs are fixed.
 - UF_CalibrateSensor and UF_DeleteAll fail sometimes due to short timeout setting.
 - UF_ScanImage does not work in firmware V1.3 or earlier.
 - UF_SearchModule sometimes fails when the baud rate is changed.

Software Version 1.0

2005-09-23

• Created.

© 2006 by Suprema Inc.